

# NATIONAL UNDERGRADUATE FELLOWSHIP PROGRAM

### FINAL REPORT

# PYRATS: Python Routines for Analyzing Transport Simulations

A suite of python classes for accessing and plotting data from GYRO/NEO/TGYRO

Author:
Micah Buuck

Supervisor: Dr. Jeff CANDY

# Contents

1	Introduction		2
	1.1	A Simple Example	2
	1.2	Command Line Use	3
	1.3	Help Files	4
2	pro	files_genData Contents	6
	2.1	Data	6
	2.2	Methods	6
3	NEO Related Classes		
	3.1	NEOObject Contents	8
		3.1.1 Data	8
		3.1.2 Methods	8
	3.2	NEOData Contents	8
		3.2.1 Data	8
		3.2.2 Methods	9
4	TGYROData Contents		10
	4.1	Data	10
	4.2	Methods	10
5	$\mathbf{G}\mathbf{Y}$	ROData Contents	13
	5.1	Data	13
	r 0	M-41 1-	1 5

# 1 Introduction

PYRATS (Python Routines for Analyzing Transport Simulations) is a data processing tool designed to make creating plots of output data from GYRO, TGYRO, or NEO easy. It makes use of the python programming language, and the associated packages numpy and matplotlib. With some knowledge of the python language and matplotlib, the typical user should be able to create plots quickly and efficiently from the python command line interpreter. First is a presentation of some of the more basic features of PYRATS. Code documentation is given on the subsequent pages.

To begin, type the following command into the terminal:

### \$ python

This will bring up the python interpreter, which is the interface you will use to interact with PYRATS. As a first example, we will look at the layout of TGYROData. Now execute the following commands:

```
>>> from pyrats.tgyro.data import TGYROData
>>> help(TGYROData)
```

This will bring up the built-in documentation for the class TGYROData. It lists all of the methods and attributes of the class, and the function of each one. This information is also contained on page x of this manual.

# 1.1 A Simple Example

TGYROData can be used to load TGYRO data with the command:

```
>>> sim1 = TGYROData('example_directory')
```

where 'example\_directory' is a directory containing TGYRO output files. The data is loaded into objects corresponding to the output file which the data came from. To create a basic plot of the particle densities and temperatures as a function of radius, type the following commands:

```
>>> import matplotlib.pyplot as plt
>>> fig = plt.figure(1)
>>> ax1 = fig.add_subplot(221)
>>> ax2 = fig.add_subplot(222)
>>> ax3 = fig.add_subplot(223)
>>> ax4 = fig.add_subplot(224)
>>> ax1.plot(sim1.data['r/a'][-1], sim1.data['te'][-1])
>>> ax2.plot(sim1.data['r/a'][-1], sim1.data['ti'][-1])
>>> ax3.plot(sim1.data['r/a'][-1], sim1.data['ne'][-1])
>>> ax4.plot(sim1.data['r/a'][-1], sim1.data['ni'][-1])
>>> ax1.set_xlabel('r/a')
>>> ax1.set_ylabel('Electron Temperature (keV)')
>>> ax2.set_xlabel('r/a')
>>> ax2.set_ylabel('Ion Temperature (keV)')
>>> ax3.set_xlabel('r/a')
>>> ax3.set_ylabel('Electron Particle Density (1/cm^3)')
```

```
>>> ax4.set_xlabel('r/a')
>>> ax4.set_ylabel('Ion Particle Density (1/cm^3)')
>>> plt.show()
```

For the TGYRO example simulation treg01, the above code produces the following plots:




Figure 1: Summary plots for an example TGYRO simulation.

## 1.2 Command Line Use

This functionality is also available from the terminal command line (as opposed to the python interpreter) with the simple command:

## \$ tgyro\_plot -p ps

When executed from the treg01 directory, the above command produces almost the same plot:




Figure 2: Summary plots for an example TGYRO simulation produced with command line tools.

# 1.3 Help Files

There is also a built in help function for PYRATS called pyrats\_help. It provieds a description of the contents of each class, and where the data is stored. It is accessed from the command line, like so:

```
~$ cd treg01
~/treg01$ pyrats_help -c
It looks like this directory contains the following file types:
neo
tgyro
profiles_gen
Try executing pyrats_help with one of these codes as the codename.
~/treg01$ pyrats_help -c neo
Please specify a NEOData method. The options are:
transport
HH_theory
CH_theory
TG_theory
S_theory
HR_theory
HS_theory
```

```
control
docstrings (not a method, instead prints the docstrings for NEOData)
~/treg01$ pyrats_help -c neo -m transport
Oupar
0vtor0
1upar
1vtor0
GAMMA
GAMMA_gv
K
PHI
ΡI
PI_gv
Q_gv
jboot
k
vpol0
```

In this case, the directory treg01 contains neo, tgyro, and profiles\_gen files. Specifying one of those codes with the -c argument then brings up the possible data containers associated with that class. More information can be gathered about a specific data container by using the -m argument.

# 2 profiles\_genData Contents

#### 2.1 Data

• data dictionary of numpy arrays - Contains all of the data read in by profiles\_genData. It is organized in a dictionary with the keys being the different column headers in the input.profiles file that is read. The keys for the dictionary can be requested with the following commands:

# \$ python

```
>>> from pyrats.profiles_gen.data import profiles_genData
```

```
>>> sim1 = profiles_genData('example_directory')
```

```
>>> sim1.data.keys()
```

where, again, 'example\_directory' is a directory containing the file input.profiles.

- n\_exp int The number of timesteps in the simulation. It is also the length of each array in data.
- **hlen** int The length of the header of file input profiles in rows.
- fignum int The number of the current active matplotlib figure.
- plotcounter int The number of the current active axes on the current active matplotlib figure.
- ar nested list of floats The sine coefficients for the r-component of the fourier series representation of the flux surfaces. Read from input.profiles.geo.
- **br** nested list of floats The cosine coefficients for the r-component of the fourier series representation of the flux surfaces. Read from input.profiles.geo.
- az nested list of floats The sine coefficients for the z-component of the fourier series representation of the flux surfaces. Read from input.profiles.geo.
- **bz** nested list of floats The cosine coefficients for the z-component of the fourier series representation of the flux surfaces. Read from input.profiles.geo.
- directory\_name str The name of the directory containing file input.profiles and possibly input.profiles.geo.

### 2.2 Methods

- \_\_init\_\_(str directory='.') This is the constructor for the class. When a new instance of the class is created, the constructor is called and executed. The only argument is the name of the directory from which to build the class, and it defaults to the current directory. It calls these methods in the following order:
  - 1. set\_directory(str directory)
  - 2. init\_data()
  - 3. store\_data()
- compplot(float inner, float outer, int n, bool verbose) This method creates overlaid flux surface plots using both the fourier series decomposition method and the shaped Grad-Shafranov Miller-type equilibrium for the flux surfaces.
  - Inner specifies the innermost flux surface to be plotted

- outer specifies the outermost flux surface to be plotted
- n specifies the number of flux surfaces to plot in between inner and outer
- if verbose is True, the legend will display the location of each flux surface
- **compute\_fouriereq**(*float* **r**) This method calculates the flux surface at radius r according to the general Grad-Shafranov Fourier-series equilibrium.
- **compute\_mtypeeq**(*float* r) This method calculates the flux surface at radius r according to the shaped Grad-Shafranov Miller-type equilibrium.
- fourierplot(float inner, float outer, int n, bool verbose) This method creates flux surface plots using only the fourier series decomposition method for the flux surfaces.
  - inner specifies the innermost flux surface to be plotted
  - outer specifies the outermost flux surface to be plotted
  - n specifies the number of flux surfaces to plot in between inner and outer
  - if verbose is True, the legend will display the location of each flux surface
- get(str var) This method returns the number array corresponding to var.
- init\_data() This method initializes all of the data objects.
- match(float val, list vec) This method finds the closest match to val in a list of values (vec) and returns the index of that value.
- millerplot(float inner, float outer, int n, bool verbose) This method creates flux surface plots using only the shaped Grad-Shafranov Miller-type equilibrium for the flux surfaces.
  - inner specifies the innermost flux surface to be plotted
  - outer specifies the outermost flux surface to be plotted
  - n specifies the number of flux surfaces to plot in between inner and outer
  - if verbose is True, the legend will display the location of each flux surface.
- plot(str var, int n1=2, int n2=2, int plotcounter=0, int fignum=0) This method creates plots of the requested data (var) using matplotlib.
  - n1 is the horizontal number of plots in one window
  - n2 is the vertical number of plots in one window
  - plotcounter is the position on which the new graph is to be placed
  - fignum is the number of the matplotlib figure on which to place the new graph
- read\_data() This method reads in data from input.profiles. It returns a dictionary containing the data that was read in.
- read\_fourier() This method reads in data from input.profiles.geo, and stores that data in the class objects ar, br, az, and bz.
- set\_directory(str directory) This method sets the class attribute directory\_name to directory.
- store\_data() This method reads data and renames it appropriately. It is necessary because the names of the different parameters are not uniformly formatted. store\_data cleans them up by inserting spaces where necessary, and by deleting #-signs when necessary.

# 3 NEO Related Classes

## 3.1 NEOObject Contents

## 3.1.1 Data

- data dictionary Holds the data associated with the object.
- units str Describes the units of the data.
- **descriptor** str Provides a description of the data.

#### 3.1.2 Methods

• \_\_init\_\_(dict data, str units, str descriptor) - This method stores the appropriate arguments in the appropriate containers.

### 3.2 NEOData Contents

#### 3.2.1 Data

- master str Holds the name of the master directory containing NEO output files.
- **directory\_name** *str* Holds the name of the currently open directory.
- fignum int The number of the current active matplotlib figure.
- plotcounter int The number of the current active axes on the current active matplotlib figure.
- toplot *list* The list of variables to plot when a plot command is called.
- transport dictionary of dictionaries of NEOObjects Contains data read in from out.neo.transport. The keys are the transport variables, each of which correspond to a NEOObject.
- **HH\_theory** dictionary of dictionaries of NEOObjects Contains data read in from out.neo.theory. The keys are the flows and fluxes predicted by the Hinton-Hazeltine model, each of which correspond to a NEOObject.
- CH\_theory dictionary of dictionaries of NEOObjects Contains data read in from out.neo.theory. The keys are the ion heat fluxes predicted by the Chang-Hinton model, each of which correspond to a NEOObject.
- **TG\_theory** dictionary of dictionaries of NEOObjects Contains data read in from out.neo.theory. The keys are the ion heat fluxes predicted by the Taguchi model, each of which correspond to a NEOObject.
- **S\_theory** dictionary of dictionaries of NEOObjects Contains data read in from out.neo.theory. The keys are the bootstrap currents predicted by the Sauter model, each of which correspond to a NEOObject.
- **HS\_theory** dictionary of dictionaries of NEOObjects Contains data read in from out.neo.theory. The keys are the fluxes predicted by the Hirshman-Sigmar model, each of which correspond to a NEOObject.

• control dictionary of dictionaries of NEOObjects - Contains data read in from out.neo.control.

#### 3.2.2 Methods

- \_\_init\_\_(str sim\_directory) Constructor that is executed when a new NEOData object is created. It takes a directory name as its argument, and then executes a top down walk down that directory. It then calls read\_data() whenever it is in a subdirectory with NEO output files. Finally, it executes store\_data()
- **get\_input**(*str* **input\_name**) Returns requested variable from input.neo.gen.
- init\_data() Initializes object data.
- plot(str var, int n1=2, int n2=2, int plotcounter=0, int fignum=0, bool legend=True, bool verbose=False, str cols='bgkcmyrw', list of strs styles=['-', '-', '--', ':']) Plots var as a matplotlib scatter plot with data from different directories coming in different colors, and different species coming in different line styles. Automatically searches for both theoretical and simulated values, and plots everything that is available.
- print\_vars() Prints all available simulated variables.
- read\_data() Read in object data. Calls read\_grid(), read\_equil(), read\_theory(), read\_transport(), read\_transport\_gv().
- read\_equil() Reads out.neo.equil. The data is eventually stored by store\_data() in control.
- read\_file() Loads data from NEO output file into buffer for manipulation and storage.
- read\_grid() Reads out.neo.grid. The data is eventually stored by store\_data() in control.
- read\_theory() Reads out.neo.theory. The data is eventually stored by store\_data() in HH\_theory, TG\_theory, CH\_theory, S\_theory, HR\_theory, and HS\_theory.
- read\_transport() Reads out.neo.transport. The data is eventually stored by store\_data() in transport.
- read\_transport\_gv() Reads out.neo.transport\_gv. The data is eventually stored by store\_data() in transport.
- **set\_directory**(*str* **path**) Sets the current directory to path.
- **split**(*list* **array**) Takes a 2-D list which has entries with multiple elements and converts it to a 2-D list with only one element per entry.
- store\_data() Stores data into data dictionaries by variable name and directory. Data can be accessed with two dictionary keys, like so: sim1.transport[parameter][directory].

# 4 TGYROData Contents

#### 4.1 Data

- loc\_n\_ion int Number of ions in simulation.
- tgyro\_mode int Mode number of TGYRO operation.
- n\_iterations int Number of TGYRO iterations in simulation.
- n\_fields int Number of fields in simulation.
- **n\_radial** int Number of radial gridpoints in simulation.
- **directory\_name** *str* Name of loaded directory.
- data dictionary of lists of numpy arrays Large dictionary containing all loaded data by variable name and then by iteration number.

### 4.2 Methods

- \_\_init\_\_(str\_sim\_directory) Constructor which is called when a new TRYGOData object is created. It calls the following methods:
  - 1.  $set\_directory(str sim\_directory)$
  - 2. init\_data()
  - 3. read\_data()
- get\_input(str input\_name) Returns the specified variable from input.tgyro.gen.
   Ex: get\_input("TGYRO\_MODE")
- get\_local\_res(int field=1, int iteration=-1) Returns a numpy array of the local field residual for the given field and iteration. The default is the last iteration, and field 1.
- get\_stability\_at\_radius(int radius=0, str frequency='r', str direction='ion') Returns a list of frequency vs. ky at specified radius from stability analysis. The parameter radius is the requested radial index; it is an integer between 0 and n\_r-1. The parameter frequency can be either the real ('r') or the imaginary ('i') spectrum. The parameter direction specifies the direction of the spectrum. It can be either the ion direction ('ion') or the electron direction ('elec').
- init\_data() Initializes object data.
- make\_gradient\_vs\_field\_plot(int r=1, int evolve\_field=1, str grad='a/LTi', str profile='ti', bool arrows=False) Return a matplotlib.pyplot figure of gradient\_vs\_field\_space. The parameter r is the radial index; it is an integer between 0 and n\_r-1. The parameters are passed to make\_gradient\_vs\_field\_space, and are described there.
- make\_gradient\_vs\_field\_space(int r=1, int evolve\_field=1, str grad='a/LTi', str profile='ti')
   Returns a matrix of Space[iteration][gradient,profile,residual] at givel radial point. eeg: Space[[4.0, 1.7, 2.5], [3.6, 1.5, 0.1]] if grad 4.0 → 3.6 while Ti → 1.5 and local residual went from 2.5 → 0.1. The parameter evolve\_field specifies the field type to pass to get\_local\_res. The parameter grad is the gradient factor to pass to get\_gradient\_factor. The parameter profile is the profile factor to pass to get\_profile\_factor.

- read\_chi\_e() Internal method. This method reads in chi\_e.out and stores it in self.chi\_e.
- read\_chi\_i() Internal method. This method reads in chi\_i.out and stores it in self.chi\_i.
- read\_control() Internal method. This method reads in control.out to set resolutions.
- read\_data() Internal method. This method reads in object data and calls the following other methods:
  - 1. read\_control()
  - 2. read\_chi\_e()
  - 3. read\_chi\_i(loc\_n\_ion)
  - 4. read\_gyrobohm()
  - 5. read\_profile()
  - 6. read\_geometry()
  - 7. read\_flux(loc\_n\_ion)
  - 8. read\_mflux(loc\_n\_ion)
  - 9. read\_gradient()
  - 10. read\_residual()
- read\_file(str file\_name) Reads TGYRO output file. Output is data['column\_header'][iteration]
- read\_flux(int num\_ions=1) Reads flux\_e.out, flux\_i(2-5).out, and flux\_target.out. Num\_ions determines how many ion files to read.
- read\_geometry() Reads and stores geometry.out in self.geometry.
- read\_gradient() Reads and stores gradient.out in self.gradient.
- read\_gyrobohm() Reads and stores gyrobohm.out in self.gyro\_bohm\_unit.
- read\_mflux() Reads and stores mflux\_e.out, mflux\_i(2-5).out, and mflux\_target.out.
- read\_num\_ions() Reads LOC\_N\_ION and stores it as self.loc\_n\_ion.
- read\_profile() Reads and stores profile.out in self.profile.
- read\_profile2() Reads and stores profile2.out in self.profile2.
- read\_profile3() Reads and stores profile3.out in self.profile3.
- read\_profile4() Reads and stores profile4.out in self.profile4.
- read\_profile5() Reads and stores profile5.out in self.profile5.
- read\_residual() Reads residual.out.
- read\_stab\_file(str file\_name) Reads files generated with stability analysis mode. The parameter file\_name is the name of the requested stability file, sich as "wi\_elec.out". It returns a list of [r, ks, freq].
- read\_stabilities() Reads output files from TGYRO\_METHOD=2, and stores them into variables, as follows:
  - wr\_ion.out  $\rightarrow$  self.wr\_ion
  - wi\_ion.out  $\rightarrow$  self.wi\_ion

- wr\_elec.out  $\rightarrow$  self.wr\_elec
- wi\_elec.out  $\rightarrow$  self.wi\_elec
- $\bullet$   ${\bf read\_tgyro\_mode}()$  Reads the TGYRO\_MODE and stores it as self.tgyro\_mode.
- **set\_directory**(*str* **sim\_directory**) Sets the simulation directory. Stores sim\_directory in self.directory\_name.

# 5 GYROData Contents

#### 5.1 Data

- **directory\_name** *str* The name of the simulation directory.
- **profile** dictionary of numpy arrays Dictionary where control information from out.gyro.profile is stored. The keys can be obtained by typing: sim1.profile.keys()
- **geometry** dictionary of numpy arrays Dictionary where geometry data from out.gyro.geometry is stored. The keys can be obtained by typing: sim1.geometry.keys()
- t dictionary of numpy arrays Dictionary where time data from t.out is stored. The keys are: 't/deltat', '(cbar\_s/a)t', and 'n\_time' which is an int, not a numpy array.
- diff numpy array Numpy array with dimensions of (n\_kinetic, n\_field, moments=2, n\_time). It contains the Gyrobohm-normalized diffusivities averaged over radius and summer over mode number. The moments are:
  - 1.  $D_{\sigma}/\chi_{GB}$  (particle diffusivity)
  - 2.  $\chi_{\sigma}/\chi_{GB}$  (energy diffusivity)
- diff\_i numpy array Numpy array with dimensions of (n\_kinetic, n\_field, moments=2, n\_x, n\_time). It contains the Gyrobohm-normalized diffusivities as a function of radius, summed over mode number. The moments are:
  - 1.  $D_{\sigma}(r)/\chi_{GB}$  (particle diffusivity)
  - 2.  $\chi_{\sigma}(r)/\chi_{GB}$  (energy diffusivity)
- diff\_n numpy array Numpy array with dimensions of (n\_kinetic, n\_field, moments=2, n\_n, n\_time). It contains the Gyrobohm-normalized diffusivities averaged over radius for each mode number. The moments are:
  - 1.  $D_{\sigma,n}/\chi_{GB}$  (particle diffusivity)
  - 2.  $\chi_{\sigma,n}/\chi_{GB}$  (energy diffusivity)
- **gbflux** numpy array Numpy array with dimensions of (n\_kinetic, n\_field, moments=4, n\_time). It contains the Gyrobohm-normalized fluxes averaged over radius and summed over mode number. The moments are:
  - 1.  $\Gamma_{\sigma}/\Gamma_{GB}$  (particle flux)
  - 2.  $Q_{\sigma}/Q_{GB}$  (energy flux)
  - 3.  $\Pi_{\sigma}/\Pi_{GB}$  (momentum flux)
  - 4.  $S_{W,\sigma}^{tur}/S_{GB}$  (exchange power density)
- **gbflux\_i** numpy array Numpy array with dimensions of (n\_kinetic, n\_field, moments=4, n\_x, n\_time). It contains the Gyrobohm-normalized fluxes as a function of mode number and averaged over radius. The moments are:
  - 1.  $\Gamma_{\sigma}(r)/\Gamma_{GB}$  (particle flux)
  - 2.  $Q_{\sigma}(r)/Q_{GB}$  (energy flux)
  - 3.  $\Pi_{\sigma}(r)/\Pi_{GB}$  (momentum flux)

- 4.  $S_{W,\sigma}^{tur}(r)/S_{GB}$  (exchange power density)
- **gbflux\_n** numpy array Numpy array with dimensions of (n\_kinetic, n\_field, moments=4, n\_n, n\_time). It contains the Gyrobohm-normalized fluxes as a function of mode number and averaged over radius. The moments are:
  - 1.  $\Gamma_{\sigma}/\Gamma_{GB}$  (particle flux)
  - 2.  $Q_{\sigma}/Q_{GB}$  (energy flux)
  - 3.  $\Pi_{\sigma}/\Pi_{GB}$  (momentum flux)
  - 4.  $S_{W.\sigma}^{tur}/S_{GB}$  (exchange power density)
- moment\_u numpy array Complex numpy array with dimensions of (n\_theta\_plot, n\_x, i\_field=n\_field, n\_n, n\_time). It contains the potential expansion coefficients. More information is available online at https://fusion.gat.com/theory/Gyrousermanual#Computed\_Quantities. The fields are described below. There can be up to three different fields:
  - 1.  $\frac{e\delta\phi_n}{T_c}$  (electrostatic potential)
  - 2.  $\frac{\bar{c}_s}{c} \frac{e\delta A_{\parallel n}}{\bar{T}_e}$  (electromagnetic potential)
  - 3.  $\frac{\delta B_{\parallel}}{B_{\text{unit}}(r)}$  (compressional perturbation)
- moment\_n numpy array Complex numpy array with dimensions of (n\_theta\_plot, n\_x, n\_kinetic, n\_n, n\_time). It contains the density moment expansion coefficients:  $\frac{\delta n_{\sigma,n}}{\bar{n}_e}$ . More information is available online at https://fusion.gat.com/theory/Gyrousermanual#Computed\_Quantities.
- moment\_e numpy array Complex numpy array with dimensions of (n\_theta\_plot, n\_x, n\_kinetic, n\_n, n\_time). It contains the energy moment expansion coefficients:  $\frac{\delta E_{\sigma,n}}{\bar{n}_e T_e}$ . More information is available online at https://fusion.gat.com/theory/Gyrousermanual#Computed\_Quantities.
- moment\_v numpy array Complex numpy array with dimensions of (n\_theta\_plot, n\_x, n\_kinetic, n\_n, n\_time). It contains the parallel velocity moment expansion coefficients:  $\frac{\delta V_{\sigma,n}}{\bar{n}_e \bar{c}_s}$ . More information is available online at https://fusion.gat.com/theory/Gyrousermanual#Computed\_Quantities.
- moment\_zero numpy array Numpy array with dimensions of (n\_x, n\_kinetic, moments=n\_moment, n\_time). It contains the flux-surface average of the n=0 component of the density and energy moments. The moments are described below. There can be up to two different moments:
  - 1.  $\langle \frac{\delta n_{\sigma,0}}{\bar{n}_e} \rangle$
  - 2.  $\langle \frac{\delta E_{\sigma,0}}{\bar{n}_e T_e} \rangle$
- flux\_velocity numpy array Numpy array with dimensions of (n\_energy, n\_lambda, n\_kinetic, i\_field=n\_field, moments=2, n\_n, n\_time). It contains the velocity-space flux densities:

$$\Gamma = \int d\varepsilon \int d\lambda \, \Gamma(\varepsilon, \lambda), \quad Q = \int d\varepsilon \int d\lambda \, Q(\varepsilon, \lambda)$$

The moments are:

- 1.  $\Gamma \sigma, n(\varepsilon, \lambda)$  (particle flux)
- 2.  $Q_{\sigma,n}(\varepsilon,\lambda)$  (energy flux)

The possible fields are:

1. electrostatic component

- 2. electromagnetic component
- **k\_perp\_squared** numpy array Numpy array with dimensions of (n\_n, n\_time). It contains the flux-surface and radial average of  $k_{\perp}^2$ :

$$\frac{\langle \langle (k_{\perp} \bar{\rho}_{s, \text{unit}})^2 | \delta \phi_n |^2 \rangle \rangle_r}{\langle \langle |\delta \phi_n|^2 \rangle \rangle_r}$$

### 5.2 Methods

- \_\_init\_\_(str sim\_directory) This is the class constructor. It is called when a new object of that class is created, and it reads in data from sim\_directory to create that object. It sets the variable directory\_name to sim\_directory, and appends the pyrats folder to the python search path. It also calls the following methods:
  - 1. init\_data()
  - 2. read\_data()
  - 3. equil\_time()
- equil\_time() This method counts the number of time steps present in the currently loaded arrays, and sets them all equal (to the length of the array with the fewest number of time steps).
- **get\_input**(str **input\_name**) This method returns the specified variable from input.gyro.gen. Ex: get\_input("TIME\_STEP")
- init\_data() This method initializes object data.
- make\_diff() This method creates self.diff by computing it from self.gbflux.
- make\_diff\_i() This method creates self.diff\_i by computing it from self.gbflux\_i.
- make\_gbflux() This method creates self.gbflux by averaging over the radial component of self.gbflux\_i.
- plot(list x, list y, tuple dim=(1, 1)) This method creates a matplotlib plot of the requested data.
- read\_data() This method reads in object data. It executes:
  - 1. read\_profile()
  - 2. read\_geometry()
  - $3. \text{ read_t}()$
  - 4. read\_gbflux\_i()
  - 5. read\_gbflux\_n()
- read\_file(str fname, int dSize) This method reads the GYRO data file named out.gyro.fname. It must be given the length in number of characters of the data elements in the file as a second argument.
- read\_flux\_velocity() This method reads in flux\_velocity data, and stores it in self.flux\_velocity.
- read\_freq() This method reads in frequency data and stores it in self.freq.
- read\_gbflux\_i() This method reads in gbflux\_i data and stores it in self.gbflux\_i.
- read\_gbflux\_n() This method reads in gbflux\_n data and stores it in self.gbflux\_n.
- read\_geometry() This method reads in geometry\_array data and stores it in self.geometry.

- read\_k\_perp\_squared() This method reads in k\_perp\_squared data and stores it in self.k\_perp\_squared.
- read\_moment\_e() This method reads in moment\_e data and stores it in self.moment\_e.
- read\_moment\_n() This method reads in moment\_n data and stores it in self.moment\_n.
- read\_moment\_u() This method reads in moment\_u data and stores it in self.moment\_u.
- read\_moment\_v() This method reads in moment\_v data and stores it in self.moment\_v.
- read\_moment\_zero() This method reads in moment\_zero data and stores it in self.moment\_zero.
- read\_profile() This method reads out.gyro.profile to get control data and stores it in self.profile.
- read\_t() This method reads tout to get time data and stores it in self.t.
- set\_directory(str path) This method sets the variable self.directory\_name to path.